

A-Sky: High-End audio player

Please, note that is a trial version and there are limitations.

Supported formats:

pcm: aiff, wav, flac, alac & cue files

dsd: dff, dsf

Supported sampling rates:

pcm: 44.1 kHz to 768 kHz

dsd: 2.8 MHz to 22.6 MHz

Output mode:

ASIO

System requirements:

2 cores processor

installed memory - at least 4 GB, of which 2.6 GB must be free

operating system - Windows 10 or newer (Windows 7 version on request)

Installation.

Installation is not required. Unpack the archive to a suitable location on the disk.

Customization.


At the first launching, a list box of the ASIO driver appears after the initial splash screen. Just click on the desired and active ASIO driver.

In the future, if a selected DAC is active, and its internal settings are unchanged, the setup mode is skipped when you start the player.

To enter the setup mode, when starting the player, click on the initial screen saver or press the "Enter" button.

When you select the ASIO driver, a settings window appears. Here you can adjust the configuration of the player.

Settings.



View cover: view the enlarged cover of the downloaded album on the right

View title: displaying the name of the folder with tracks

View track time: displaying the duration of the track


Location: location of the player on the screen

Drive scan settings

drive: select drive to scan


folder name (optional): first-level folder name template, case sensitive, if the directory name is longer than 20 characters, it is shortened to 19 characters plus * at the end

library name (optional): library display name



Recommended directory structure: Library\Artist\Album\Tracks

Control.



To control the player, use the on-screen buttons.

Open album – double-click.

Enlarge cover – click on the cover of the current album on the right

Search by libraries – F1, search is carried out by artists and albums

Short keys:

"PageUp" – scroll the library up

"PageDown" – scroll down the library

"P" – play

"S" – stop

"N" –next

"Space" – play / pause

"O" – open

"Up" – select a track one position up

"Down" – select a track one position down

"Keypad 8" – scroll the playlist up

"Keypad 2" – scroll down the playlist

"Shift + Up" – move a track one position up

"Shift + Down" – move a track one position down

"Delete" – delete a track

"C" – clear playlist

Library search:

"F1" – start searching

"Esc" – exit search

"Enter" – find

Covers.

The format of the cover is "png" or "jpg"

The name of the cover is "cover", "front" or "folder"

The location of the cover - where the tracks are, or in the subdirectory "Art"

Other.

The ASIO driver buffer is set on the value recommended by the DAC manufacturer or higher.

You can open tracks only with the same sample rate at the same time.

<http://clearsound.club/#>